

**PsiLoc Crystal  
Cyrillic on EPOC  
Localisation Package**  
for  
Nokia 9210/9290 Communicator


PSI NT (PSILoc)  
<http://www.psiloc.com/>

Application Guide

## Introduction

**PsiLoc Crystal Cyrillic on EPOC** is localisation package, which includes all components indispensable for displaying and entering the information in specified country language.

**PsiLoc Crystal Cyrillic on EPOC** package provides national keyboard layout, names of days and months, date format, national system fonts and sorting methods using your national characters.



Furthermore, **PsiLoc Crystal** provides appropriate code pages and character encodings in N9210's Messaging application.

**PsiLoc Crystal Cyrillic on EPOC** supports following languages: **Azeri, Belarusian, Bulgarian, Kazakh, Macedonian, Russian, Serbian, Tatar, Ukrainian and Uzbek.**

## Entering text

**PsiLoc Crystal** allows entering the text in your national language. You can use two keyboard sets. One is the default keyboard set and the second is keyboard set specific to your language. The key combination for switching the keyboard set is defined in PsiLoc configuration.



## PsiLoc Crystal configuration

When PsiLoc Crystal is installed the additional icon (applet) **Crystal** appears in **Control Panel**. You can use this applet to configure the PsiLoc package. The configuration window has 3 property sheets.

**1. PsiLoc Crystal** - This sheet contains basic settings of localisation package.

- **Enable *nnnn* on EPOC** (*nnnn* is the name of your localisation) – this setting allows you **switching** the localisation **on** and **off** (by selecting **Yes** or **No**). After changing this setting your communicator will be restarted.
- **Your country** – here you have to define your country.
- **Load localization library** – you can switch off localization library (which is responsible for translation of day and month names, date and time format etc.). Note that this option is unavailable in some versions of PsiLoc.

**2. Encodings** - This sheet contains settings of encoding in e-mail messages.

- **Email format** – you can select the encoding which will be used in email editor.

**3. Advanced** -This sheet contains advanced settings.

- **Locale identifier** – you can switch on or off the locale identifier which is displayed in left upper corner of the 9210 screen.
- **Change keyboard set** – here you can define a shortcut for switching between two keyboard sets available in PsiLoc.
- **Country identifier** – here you can define the country identifier which will be set by PsiLoc Crystal. Note that some applications use this identifier and may not work properly with any setting.
- **Change system fonts** – you can decide whether your default system fonts will be changed by PsiLoc Crystal (select **Yes** or **No**).

## Reviews

Review of PsiLoc Crystal packages can be found at following Web site:

[My-Communicator.com](http://My-Communicator.com)

## **Purchasing & Contact Information**

Current versions of PsiLoc Crystal packages can be obtained at:

<http://www.psiloc.com>

Should you have any questions or comments, please write to:

[info@psiloc.com](mailto:info@psiloc.com)