

Extended Printers

for
Nokia 9210/9290 Communicator

PSI NT (PSILoc)
<http://www.psiloc.com/>

Installation Guide

Installation


Before installing this version of **Extended Printers** package you have to uninstall any previous versions installed in your machine (if any). In order to uninstall previous version launch **Install/Remove** application, select **Extended Printers** from the list of installed applications and press **Remove** button.

Now you can install the newest version. **Extended Printers** package is delivered in form of standard SIS installation file. You have to perform the installation process of this file according to your Nokia Communicator User Manual:


1. Check whether **PC Suite** application is running on your PC. If not – start it.
2. Connect your Nokia Communicator to PC using standard **data cable** (DLR-2L) and wait for PC Suite to establish connection with Communicator



3. Double-click your **SIS** file using left mouse button – this will launch PC Suite's Installer.



4. Select **destination disk** for the installation. Choose **C:** drive (internal memory) if you work with multiple memory cards to assure functionality of the localisation package even if the card is removed/changed or **D:** drive (memory card) if you work with single MMC card to conserve internal memory.



Installation is complete. Now you can start using the program in the same way as any other printer driver. Please, **register** Extended Printers by entering **registration code**. If you don't have registration code, Extended Printers will be started in time-limited trial version.